

Oracle® Database

Client Quick Installation Guide

11g Release 1 (11.1) for Linux x86

B32282-03

September 2007

This guide describes how to quickly install Oracle Database 11g on Linux x86 systems. It includes information about the following:

- [Reviewing Information About This Guide](#)
- [Logging In to the System as root](#)
- [Checking the Hardware Requirements](#)
- [Checking the Software Requirements](#)
- [Creating Required Operating System Groups and Users](#)
- [Creating Required Directories](#)
- [Configuring the oracle User's Environment](#)
- [Mounting the Product Disc](#)
- [Installing Oracle Database Client](#)
- [What to Do Next?](#)
- [Documentation Accessibility](#)

1 Reviewing Information About This Guide

This guide describes how to complete a default installation of Oracle Database Client on a system that does not have any Oracle software installed on it. It describes how to install one of the following installation types:

- **Administrator:** Enables applications to connect to an Oracle Database instance on the local system or on a remote system. It also provides tools that enable you to administer Oracle Database.
- **Runtime:** Enables applications to connect to an Oracle Database instance on the local system or on a remote system.
- **Instant Client:** Enables you to install only the shared libraries required by Oracle Call Interface (OCI), Oracle C++ Call Interface (OCCI), Pro*C, or Java database connectivity (JDBC) OCI applications. This installation type requires much less disk space as compared to the other Oracle Database Client installation types.

See Also: *Oracle Call Interface Programmer's Guide* for more information about Instant Client

This guide does not describe how to install the Custom installation type.

Where to Get Additional Installation Information

For more detailed information about installing Oracle Database Client, refer to *Oracle Database Client Installation Guide for Linux*.

This guide is available on the product disc. To access it, use a Web browser to open the `welcome.htm` file located in the top-level directory of the installation media, and then select the **Documentation** tab.

2 Logging In to the System as root

Before you install the Oracle software, you must complete several tasks as the `root` user. To log in as the `root` user, complete one of the following procedures:

Note: Unless you intend to complete a silent-mode installation, you must install the software from an X Window System workstation, an X terminal, or a PC or other system with X server software installed.

- Following are the steps for installing the software from an X Window System workstation or X terminal:

1. Start a local terminal session, for example, an X terminal (`xterm`).
2. If you are not installing the software on the local system, then enter the following command to enable the remote host to display X applications on the local X server:

```
$ xhost fully_qualified_remote_host_name
```

For example:

```
$ xhost somehost.us.example.com
```

3. If you are not installing the software on the local system, then use the `ssh`, `rlogin`, or `telnet` command to connect to the system where you want to install the software:

```
$ telnet fully_qualified_remote_host_name
```

4. If you are not logged in as the `root` user, then enter the following command to switch user to `root`:

```
$ sudo sh
password:
#
```

- Following are the steps for installing the software from a PC or other system with X server software:

Note: If necessary, refer to your X server documentation for more information about completing this procedure. Depending on the X server software that you are using, you may need to complete the tasks in a different order.

1. Start the X server software.

2. Configure the security settings of the X server software to permit remote hosts to display X applications on the local system.
3. Connect to the remote system where you want to install the software and start a terminal session on that system, for example, an X terminal (`xterm`).
4. If you are not logged in as the `root` user on the remote system, then enter the following command to switch user to `root`:

```
$ sudo sh
password:
#
```

3 Checking the Hardware Requirements

The system must meet the following minimum hardware requirements:

- [Memory Requirements](#)
- [Disk Space Requirements](#)

3.1 Memory Requirements

The following are the memory requirements for installing Oracle Database 11g release 1:

- At least 256 MB of physical RAM.

To determine the physical RAM size, enter the following command:

```
# grep MemTotal /proc/meminfo
```

If the size of the physical RAM is less than the required size, then you must install more memory before continuing.

- The following table describes the relationship between installed RAM and the configured swap space requirement:

| Available RAM | Swap Space Required |
|-----------------------------|----------------------------|
| Between 257 MB and 512 MB | Double the size of RAM |
| Between 513 MB and 2048 MB | 1.5 times the size of RAM |
| Between 2049 MB and 8192 MB | Equal to the size of RAM |
| More than 8192 MB | 0.75 times the size of RAM |

- To determine whether the system architecture can run the software, enter the following command:

```
# grep "model name" /proc/cpuinfo
```

Note: This command displays the processor type. Verify that the processor architecture matches the Oracle software release that you want to install. If you do not see the expected output, then you cannot install the software on this system.

To determine the size of the configured swap space, enter the following command:

```
# grep SwapTotal /proc/meminfo
```

If necessary, refer to the operating system documentation for information about how to configure additional swap space.

To determine the available RAM and swap space, enter the following command:

```
# free
```

Note: Oracle recommends that you take multiple values for the available RAM and swap space before finalizing a value. This is because the available RAM and swap space keep changing depending on the user interactions with the computer.

3.2 Disk Space Requirements

The following are the disk space requirements for installing Oracle Database 11g release 1:

- The minimum disk space requirement for a client install in the `/tmp` directory is 130 MB.

To determine the amount of disk space available in the `/tmp` directory, enter the following command:

```
# df -k /tmp
```

If there is less than 400 MB of free disk space available in the `/tmp` directory, then complete one of the following steps:

- Delete unnecessary files from the `/tmp` directory to meet the disk space requirement.
 - Set the `TMP` and `TMPDIR` environment variables when setting the `oracle` user's environment (described later).
 - Extend the file system that contains the `/tmp` directory. If necessary, contact the system administrator for information about extending file systems.
- Between 34 MB and 820 MB of disk space for the Oracle software, depending on the installation type

To determine the amount of free disk space on the system, enter the following command:

```
# df -k
```

| Installation typr | Requirement for Software Files (MB) |
|-------------------|-------------------------------------|
| Instant Client | 150 |
| Administrator | 935 |
| Runtime | 660 |
| Custom (maximum) | 850 |

4 Checking the Software Requirements

Depending on the products that you intend to install, verify that the following softwares are installed on the system.

- [Operating System Requirements](#)
- [Kernel Requirements](#)
- [Package Requirements](#)
- [Compiler Requirements](#)
- [Additional Software Requirements](#)

4.1 Operating System Requirements

The following are the operating system requirements for Oracle Database 11g release 1:

- Asianux 2.0
- Asianux 3.0
- Oracle Enterprise Linux 4.0
- Oracle Enterprise Linux 5.0
- Red Hat Enterprise Linux 4.0
- Red Hat Enterprise Linux 5.0
- SUSE Enterprise Linux 10.0

To determine the distribution and version of Linux installed, enter the following command:

```
# cat /proc/version
```

Note: Only the distributions and versions listed in the earlier itemized list are supported. Do not install the software on other versions of Linux.

4.2 Kernel Requirements

The following are the Kernel requirements for Oracle Database 11g release 1:

- For Asianux 2, Oracle Enterprise Linux 4.0, and Red Hat Enterprise Linux 4.0:
2.6.9
- For Asianux 3, Oracle Enterprise Linux 5.0, and Red Hat Enterprise Linux 5.0:
2.6.18
- For SUSE 10:
2.6.16.21

To determine whether the required kernel is installed, enter the following command:

```
# uname -r
```

The following is a sample output displayed by running this command on a Red Hat Enterprise Linux 4.0 system:

```
2.6.9-34.0.1.0.11.ELsmp
```

In this example, the output shows the kernel version (2.6.9) and errata level (34.0.1.0.11) on the system.

If the kernel version does not meet the requirement specified earlier in this section, then contact the operating system vendor for information about obtaining and installing kernel updates.

4.3 Package Requirements

The following are the list of packages required for Oracle Database 11g release 1:

- The following or later version of packages for Asianux 2, Oracle Enterprise Linux 4.0, and Red Hat Enterprise Linux 4.0 should be installed:

```
binutils-2.15.92.0.2-18
compat-libstdc++-33.2.3-47.3
elfutils-libelf-0.97-5
elfutils-libelf-devel-0.97-5
glibc-2.3.4-2.19
glibc-common-2.3.4-2.19
glibc-devel-2.3.4-2.19
glibc-headers-2.3.4-2.19
gcc-3.4.5-2
gcc-c++-3.4.5-2
libaio-devel-0.3.105-2
libaio-0.3.105-2
libgcc-3.4.5
libstdc++-3.4.5-2
libstdc++-devel-3.4.5-2
make-3.80-5
sysstat-5.0.5
unixODBC-2.2.11
unixODBC-devel-2.2.11
```

- The following or later version of packages for Asianux 3, Oracle Enterprise Linux 5.0, and Red Hat Enterprise Linux 5.0 should be installed:

```
binutils-2.17.50.0.6-2.e15
compat-libstdc++-33-3.2.3-61
elfutils-libelf-0.125-3.e15
elfutils-libelf-devel-0.125
glibc-2.5-12
glibc-common-2.5-12
glibc-devel-2.5-12
glibc-headers-2.5-12
gcc-4.1.1-52
gcc-c++-4.1.1-52
libaio-0.3.106
libaio-devel-0.3.106
libgcc-4.1.1-52
libstdc++-4.1.1
libstdc++-devel-4.1.1-52.e15
make-3.81-1.1
```

```
sysstat-7.0.0
unixODBC-2.2.11
unixODBC-devel-2.2.11
```

- The following or later version of packages for SUSE Linux Enterprise Server 10 should be installed:

```
binutils-2.16.91.0.5
compat-libstdc++-5.0.7
glibc-2.4-31.2
glibc-devel-2.4-31.2
gcc-4.1.0
ksh-93r-12.9
libaio-0.3.104
libaio-devel-0.3.104
libelf-0.8.5
libgcc-4.1.0
libstdc++-4.1.0
libstdc++-devel-4.1.0
make-3.80
sysstat-6.0.2
unixODBC-2.2.11
unixODBC-devel-2.2.11
```

Note: If you did not perform a default Linux installation, you intend to use LDAP, and you want to use the scripts `odisrvreg`, `oidca`, or `schemasync`, then install the Korn shell RPM for your Linux distribution.

To determine whether the required packages are installed, enter commands similar to the following:

```
# rpm -q package_name
```

If a package is not installed, then install it from the Linux distribution media or download the required package version from the Linux vendor's Web site.

4.4 Compiler Requirements

The following are the compiler requirements for Pro*C/C++ , Oracle Call Interface, Oracle C++ Call Interface, and Oracle XML Developer's Kit (XDK) with Oracle Database 11g release 1:

Intel C++ Compiler 9.1 or later and the version of GNU C and C++ compilers listed under "[Package Requirements](#)" on page 6 are supported with these products.

Note: Intel Compiler v9.1 can be used only with gcc 3.4.5 or gcc 4.0 or gcc 4.1 standard template libraries to build Oracle C++ Call Interface (OCCI) applications.

Oracle XML Developer's Kit is supported with the same compilers as OCCI.

4.5 Additional Software Requirements

Depending on the components you want to use, you must ensure that the following software are installed:

- [Oracle ODBC Drivers](#)
- [Integrated Development Environment](#)
- [Oracle Messaging Gateway](#)
- [Browser Requirements](#)
- [Programming languages](#)

4.5.1 Oracle ODBC Drivers

You should install ODBC Driver Manager for UNIX. You can download and install the Driver Manager from the following URL:

<http://www.unixodbc.org>

4.5.2 Integrated Development Environment

You can use the following optional JDK versions with the Oracle JDBC/OCI drivers. However, these are not mandatory for the installation:

- Sun JDK 1.4.2_08 with the JNDI extension
- Sun JDK 1.5.0-06 with the JNDI extension

4.5.3 Oracle Messaging Gateway

Oracle Messaging Gateway supports the integration of Oracle Streams Advanced Queuing (AQ) with the following software:

- IBM WebSphere MQ V5.3, client and server, with corrective service diskette 5 (CSD05) or later:

MQSeriesClient
MQSeriesServer
MQSeriesRuntime

- TIBCO Rendezvous 7.2

If you require a CSD for WebSphere MQ, then refer to the following Web site for download and installation information:

<http://www-306.ibm.com/software/integration/wmq/support>

4.5.4 Browser Requirements

Web browsers must support Java Script and the HTML 4.0 and CSS 1.0 standards. The following Web browsers are supported for Oracle Enterprise Manager Database Control:

- Netscape Navigator 7.2
- Netscape Navigator 8.1
- Mozilla version 1.7
- Microsoft Internet Explorer 6.0 SP2
- Microsoft Internet Explorer 7.0
- Firefox 1.0.4

- Firefox 1.5
- Firefox 2.0

4.5.5 Programming languages

The following products are certified for use with Pro*COBOL:

- Acucorp ACUCOBOL-GT 6.2
- Micro Focus Server Express 4.0 SP2

The following product is certified for use with Pro*FORTRAN:

XL Fortran Advanced Edition V9.1.1 (or later) for Linux

5 Creating Required Operating System Groups and Users

The following local operating system groups and users are required if you are installing Oracle Database:

- The Oracle Inventory group (`oinstall`)
- The Oracle software owner (`oracle`)

To determine whether these groups and users already exist, and if necessary, to create them, follow these steps:

1. To determine whether the `oinstall` group exists, enter the following command:

```
# more /etc/oraInst.loc
```

If the output of this command shows the `oinstall` group name, then the group already exists.

If the `oraInst.loc` file exists, then the output from this command is similar to the following:

```
inventory_loc=/u01/app/oraInventory
inst_group=oinstall
```

The `inst_group` parameter shows the name of the Oracle Inventory group, `oinstall`.

2. If necessary, enter the following commands to create the `oinstall` group:

```
# /usr/sbin/groupadd oinstall
```

3. To determine whether the `oracle` user exists and belongs to the correct groups, enter the following command:

```
# id oracle
```

If the `oracle` user exists, then this command displays information about the groups to which the user belongs. The output should be similar to the following, indicating that `oinstall` is the primary group and `dba` is a secondary group:

```
uid=440(oracle) gid=200(oinstall) groups=201(dba),202(oper)
```

4. If necessary, complete one of the following actions:

- If the `oracle` user exists, but its primary group is not `oinstall` or it is not a member of the `dba` group, then enter the following command:

```
# /usr/sbin/usermod -g oinstall -G dba oracle
```

- If the `oracle` user does not exist, enter the following command to create it:

```
# /usr/sbin/useradd -g oinstall -G dba oracle
```

This command creates the `oracle` user and specifies `oinstall` as the primary group and `dba` as the secondary group.

5. Enter the following command to set the password of the `oracle` user:

```
# passwd oracle
```

6 Creating Required Directories

Note: If you do not want to create a separate Oracle data file directory, then you can install the data files in a subdirectory of the Oracle base directory. However, this is not recommended for production databases.

To create the Oracle base directory:

1. Enter the following command to display information about all mounted file systems:

```
# df -h
```

This command displays information about all the file systems mounted on the system, including:

- The physical device name
 - The total amount, used amount, and available amount of disk space
 - The mount point directory for that file system
2. From the display, identify either one or two file systems that meet the disk space requirements mentioned earlier in this section.
 3. Note the name of the mount point directory for each file system that you identified.
 4. Enter commands similar to the following to create the recommended subdirectories in the mount point directory that you identified and set the appropriate owner, group, and permissions on them:

```
# mkdir -p /mount_point/app/  
# chown -R oracle:oinstall /mount_point/app/  
# chmod -R 775 /mount_point/app/
```

For example:

```
# mkdir -p /u01/app/  
# chown -R oracle:oinstall /u01/app/  
# chmod -R 775 /u01/app/
```

7 Configuring the oracle User's Environment

You run Oracle Universal Installer from the `oracle` account. However, before you start Oracle Universal Installer, you must configure the environment of the `oracle` user. To configure the environment, you must:

- Set the default file mode creation mask (`umask`) to 022 in the shell startup file.
- Set the `DISPLAY` environment variable.

To set the `oracle` user's environment:

1. Start a new terminal session, for example, an X terminal (`xterm`).
2. Enter the following command to ensure that X Window applications can display on this system:

```
$ xhost fully_qualified_remote_host_name
```

For example:

```
$ xhost somehost.us.example.com
```

3. Complete one of the following steps:
 - If the terminal session is not connected to the system where you want to install the software, then log in to that system as the `oracle` user.
 - If the terminal session is connected to the system where you want to install the software, then switch user to `oracle`:

```
$ su - oracle
```

4. To determine the default shell for the `oracle` user, enter the following command:

```
$ echo $SHELL
```

5. Open the `oracle` user's shell startup file in any text editor:

- Bash shell (`bash`) on SUSE:

```
$ vi .profile
```

- Bourne shell (`sh`), Bash shell on Red Hat (`bash`), or Korn shell (`ksh`):

```
$ vi .bash_profile
```

- C shell (`csh` or `tcsh`):

```
% vi .login
```

6. Enter or edit the following line in the shell startup file, specifying a value of 022 for the default file mode creation mask:

```
umask 022
```

7. If the `ORACLE_SID`, `ORACLE_HOME`, or `ORACLE_BASE` environment variable is set in the file, then remove the corresponding lines from the file.

8. Save the file, and exit from the editor.

9. To run the shell startup script, enter the following command:

- Bash shell on Red Hat:

```
$ . ~/.bash_profile
```

- Bourne shell, Bash shell on SUSE, or Korn shell:

```
$ . ~/.profile
```

- C shell:

```
% source ~/.login
```

10. If you are not installing the software on the local system, then enter a command similar to the following to direct X applications to display on the local system:

- Bourne, Bash, or Korn shell:

```
$ DISPLAY=local_host:0.0 ; export DISPLAY
```

- C shell:

```
% setenv DISPLAY local_host:0.0
```

In this example, *local_host* is the host name or IP address of the system that you want to use to display Oracle Universal Installer (your workstation or PC).

11. If you determined that the `/tmp` directory had insufficient free disk space when checking the hardware requirements, then identify a file system with the required amount of free space and set the `TMP` and `TMPDIR` environment variables as follows:

- a. Use the `df -k` command to identify a suitable file system with sufficient free space.
- b. If necessary, enter commands similar to the following to create a temporary directory on the file system that you identified, and set the appropriate permissions on the directory:

```
# sudo mkdir /mount_point/tmp
# sudo chmod a+wr /mount_point/tmp
# exit
```

- c. Enter commands similar to the following to set the `TMP` and `TMPDIR` environment variables:

Bourne, Bash, or Korn shell:

```
$ TMP=/mount_point/tmp
$ TMPDIR=/mount_point/tmp
$ export TMP TMPDIR
```

C shell:

```
% setenv TMP /mount_point/tmp
% setenv TMPDIR /mount_point/tmp
```

12. Enter the following commands to ensure that the `ORACLE_HOME` and `TNS_ADMIN` environment variables are not set:

Bourne, Bash, or Korn shell:

```
$ unset ORACLE_HOME
```

```
$ unset TNS_ADMIN
```

C shell:

```
% unsetenv ORACLE_HOME  
% unsetenv TNS_ADMIN
```

13. To verify that the environment has been set correctly, enter the following commands:

```
$ umask  
$ env | more
```

Verify that the `umask` command displays a value of 22, 022, or 0022 and the environment variables that you set in this section have the correct values.

8 Mounting the Product Disc

On most Linux systems, the product disc mounts automatically when you insert it into the drive. If the disc does not mount automatically, then follow these steps to mount it:

1. Enter a command similar to the following to eject the currently mounted disc, then remove it from the drive:
 - Asianux, Oracle Enterprise Linux, and Red Hat Enterprise Linux:

```
$ sudo eject /mnt/dvd
```
 - SUSE:

```
# eject /media/dvd
```
- In these examples, `/mnt/dvd` and `/media/dvd` are the mount point directories for the disc drive.
2. Insert the DVD into the disc drive.
 3. To verify that the disc mounted automatically, enter a command similar to the following:
 - Asianux, Oracle Enterprise Linux, and Red Hat Enterprise Linux:

```
# ls /mnt/dvd
```
 - SUSE:

```
# ls /media/dvd
```
 4. If this command fails to display the contents of the disc, then enter a command similar to the following:
 - Asianux, Oracle Enterprise Linux, and Red Hat Enterprise Linux:

```
# mount -t iso9660 /dev/dvd /mnt/dvd
```
 - SUSE:

```
# mount -t iso9660 /dev/dvd /media/dvd
```

In these examples, `/mnt/dvd` and `/media/dvd` are the mount point directories for the disc drive.

9 Installing Oracle Database Client

After configuring the `oracle` user's environment, start Oracle Universal Installer and install Oracle Database as follows:

- To start Oracle Universal Installer, enter the following command:

```
$ /mount_point/db/runInstaller
```

If Oracle Universal Installer does not start, then refer to *Oracle Database Installation Guide for Linux* for information about how to troubleshoot X Window display problems.

- The following table describes the recommended action for each Oracle Universal Installer screen. Use the following guidelines to complete the installation:
 - If you need more assistance, or if you want to choose an option that is not a default, then click **Help** for additional information.
 - If you encounter errors while installing or linking the software, then refer to *Oracle Database Installation Guide for Linux* for information about troubleshooting.

Note: If you have completed the tasks listed previously, then you can complete the installation by choosing the default values on most screens.

1. In the Select a Product to Install screen, select the product that you want to install: **Oracle Database 11g**, **Oracle Client**, or **Oracle Clusterware**.
In order to install Oracle Client, select **Oracle Client** and click **Next**.
2. In the Select Installation Type screen, select the type of installation that you want: **Instant Client**, **Administrator**, **Runtime**, or **Custom** and click **Next**.
3. In the Product-specific Prerequisite Checks screen, correct any errors that Oracle Universal Installer may have found, and then click **Next**.
4. In the Summary screen, check the installed components listing and click **Install**.
5. If you have selected the Administrator or Runtime installation type, then Net Configuration Assistant is invoked as a part of the installation. Click **Next** to complete the installation. You should then start the Net Configuration Assistant to complete configuration process.
6. In the Oracle Net Configuration Assistant: Welcome screen, either select **Perform typical configuration** to use a default configuration, or select the **Naming Methods** configuration option. Then click **Next**. (The remaining steps in this procedure assume you are using Naming Methods.)
7. Answer the remaining prompts to complete the configuration.
8. On the Execute Configuration Scripts screen, read the instructions and then run the script mentioned on this screen. Click **OK** to continue.

9. In the End of Installation screen, click **Exit**, then click **Yes** to exit from Oracle Universal Installer.

10 What to Do Next?

After you have successfully installed Oracle Database Client, refer to *Oracle Database Client Installation Guide for Linux* for information about required and optional postinstallation steps.

11 Documentation Accessibility

Our goal is to make Oracle products, services, and supporting documentation accessible, with good usability, to the disabled community. To that end, our documentation includes features that make information available to users of assistive technology. This documentation is available in HTML format, and contains markup to facilitate access by the disabled community. Accessibility standards will continue to evolve over time, and Oracle is actively engaged with other market-leading technology vendors to address technical obstacles so that our documentation can be accessible to all of our customers. For more information, visit the Oracle Accessibility Program Web site at

<http://www.oracle.com/accessibility/>

Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

TTY Access to Oracle Support Services

Oracle provides dedicated Text Telephone (TTY) access to Oracle Support Services within the United States of America 24 hours a day, 7 days a week. For TTY support, call 800.446.2398. Outside the United States, call +1.407.458.2479.

Oracle Database Client Quick Installation Guide, 11g Release 1 (11.1) for Linux x86
B32282-03

Copyright © 2007, Oracle. All rights reserved.

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software—Restricted Rights (June 1987). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

Oracle, JD Edwards, and PeopleSoft are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.